




Installing RASWin license for servers (Server Side Instructions):

- 1) Install the Sentinel LDK Runtime from one of the following links:


Official Sentinel Link:

<https://sentinelcustomer.gemalto.com/DownloadNotice.aspx?dID=8589947119>

- 2) Download and Unpack the zip file **RTEVendor.zip**. You can download this file from the following mirror link: <http://www.raswin.eu/raswinupdates/VendorRTE.zip>
- 3) Run the file **update_vendor.bat** inside the zip on step 2, make sure you deactivate any Antivirus and that you've admin rights, otherwise RTE installation may fail.
- 4) Start the **Sentinel Admin Control Center** opening the following url: <http://localhost:1947>
- 5) Go to left Menu **Configuration, Network Tab**, and make sure you see the URL <http://85.59.44.213:8082>, in the EMS URL edit box. If not, type it there. Also make sure the network visibility option is set to: **All Network Adapters**. **Click Submit for the changes to take effect.**



- 6) Configure the users in your network that will have access to the License server in the tab **Users**.



Ensure **User Restrictions** are allow=all@all (in case you don't want to limit access per user), If you want to personalize access click on **Show Recent users**. On the list click each user you want to grant access by pressing "allow" or "deny".

- 7) Finally activate your RASWin server license by going to the following URL and entering the provided **Product Key**. <http://85.59.44.213:8082/ems/customerLogin.html>

Client Side Configuration

- 1) After Installation of RASWin software, on your Client machine start **Sentinel Admin Control Panel** using the following URL: <http://localhost:1947>
- 2) Go to **Configuration** on the left menu.
- 3) Click on tab **Access To Remote License Managers**.
- 4) In the **Remote License Search parameters** enter the server IP address.



C:\Program Files (x86)\Common Files\Aladdin Shared\HASP\hasplm.ini

- 5) Go to tab **Allow Access to remote License Managers**, make sure you've the **Allow Access to Remote Licenses** checked. In some strange situations also the **Aggressive Search for Remote Licenses** will also be required but leave it unchecked if you don't need it.