



## Configure RASWin license for servers and clients:

**Prerequisites:** Sentinel ACC is required, this is installed either manually or automatically after RASWin installation.

### Server side configuration

- 1) Start Sentinel Admin Control panel on the server using your web browser with this url:  
**http://localhost:1947.**
- 2) Go to **Configuration** on the left menu.
- 3) Click on tab **Users**.

The screenshot shows the 'Sentinel Admin Control Center' interface. The left sidebar contains a menu with 'Configuration' selected. The main area is titled 'Configuration Host Name: manel-pc' and has four tabs: 'Basic Settings', 'Users', 'Access to Remote License Managers', and 'Access from Remote Clients'. The 'Users' tab is active, showing 'User Restrictions' with a text input field containing 'allow=all@all'. Below the input field is a 'Show Recent Users' button. At the bottom right, there are 'Submit', 'Cancel', and 'Set Defaults' buttons. A note at the bottom right states: 'The entries are evaluated in the order in which they are specified. As so allow\*@\* is implicitly added to end of list'.

- 4) Ensure **User Restrictions** are allow=all@all
- 5) If you want to personalize access click on **Show Recent users**
- 6) On the list click each user you want to grant access by pressing “allow” or “deny”.

### Client Side Configuration

- 1) On your Client machine start Sentinel Admin Control Panel opening the following URL:  
<http://localhost:1947>
- 2) Go to **Configuration** on the left menu.
- 3) Click on tab **Access To Remote License Managers**.
- 4) In the **Remote License Search parameters** enter the server ip.

The screenshot shows the 'Sentinel Admin Control Center' interface. The left sidebar contains a menu with 'Configuration' selected. The main area is titled 'Configuration Host Name: manel-pc' and has four tabs: 'Basic Settings', 'Users', 'Access to Remote License Managers', and 'Access from Remote Clients'. The 'Access to Remote License Managers' tab is active, showing 'Allow Access to Remote Licenses' and 'Broadcast Search for Remote Licenses' both checked. Below these is a 'Remote License Search Parameters' section with a text input field containing 'your ip server here'. At the bottom right, there are 'Submit', 'Cancel', and 'Set Defaults' buttons. A note at the top right states: 'You may experience a delay of a few minutes before your chang'.