



Process to install RASWin RTE Manually

Method 1 (RASWin installed on the computer)

Prerequisites: RASWin installed on your computer.

Browse to the location where RASWin is installed, usually:

C:\Program Files (x86)\SolidSafe\RASWin vX.X.X\RTE

Where X.X.X is the version of RASWin, there the user will see the following files:

 EMSURLUpdater.exe	06/03/2017 16:59	Aplicación	35 KB
 haspdinst.exe	11/10/2018 11:50	Aplicación	20.596 KB
 RASWinHasp.exe	11/10/2018 11:52	Aplicación	15.593 KB
 update_vendor.bat	08/09/2016 15:31	Archivo por lotes ...	1 KB

Execute the file marked in yellow **update_vendor.bat**, wait until you get a successful installation message. The RTE is now installed.

- Method 2 (for servers or when RASWin is not installed)

Prerequisites: None.

Download the RTE from here:

<http://www.raswin.eu/raswinupdates/VendorRTE.zip>

Unzip the downloaded file into a folder of your choice and navigate to it. The following files will be shown there.

 EMSURLUpdater.exe	06/03/2017 16:59	Aplicación	35 KB
 haspdinst.exe	11/10/2018 11:50	Aplicación	20.596 KB
 RASWinHasp.exe	11/10/2018 11:52	Aplicación	15.593 KB
 update_vendor.bat	08/09/2016 15:31	Archivo por lotes ...	1 KB

Execute the file marked in yellow **update_vendor.bat**, wait until you get a successful installation message. The RTE is now installed.