



Enable the Network License Server to Detach License Keys

1 - On the server, open a browser and go to <http://localhost:1947>. The **Sentinel Admin Control Center** appears.

2-In the **Options** pane on the left, click **Configuration**, and click the **Detachable Licenses** tab.

The screenshot shows the Sentinel Admin Control Center interface. The left sidebar contains the following menu items: Sentinel Keys, Products, Features, Sessions, Update/Attach, Access Log, Configuration (highlighted), and Diagnostics. The main content area is titled 'Configuration' with a subtitle 'Host Name: manel-pc'. It features several tabs: Basic Settings, Users, Access to Remote License Managers, Access from Remote Clients, Client Identities, and Detachable Licenses (circled in blue). The Detachable Licenses tab is active, displaying the following settings:

- On-Demand Detaching of Licenses**: Enabled (checked checkbox).
- Maximum Duration @**: 14 days.
- Automatic Detaching of Licenses**: Enabled (unchecked checkbox).
- Allowed Offline Duration @**: 2 hours.
- Common Detach Settings**: Reserved Licenses @ 0 but at least 0 % of total licenses.
- Per Product Settings**: A 'Configure' button.

At the bottom of the configuration area are three buttons: Submit, Cancel, and Set Defaults.

3 - Check **On-Demand Detaching of Licenses**. In the **Initial Detach Limits** section, you may also set the number of **Reserved Licenses** that are to remain non-detachable and the **Max. Duration** in days, which automatically restores the license to the server after the set number of days has expired.

Click **Submit**.



Enable the Client Computer to Detach License Keys

1. On the client computer that needs a key for working the network, open a browser and go to <http://localhost:1947>. The **Sentinel Admin Control Center** appears.
2. In the **Options** pane on the left, click **Configuration**, and click the **Detachable Licenses** tab.

Sentinel Admin Control Center

Configuration Host Name: manet-pc

Basic Settings Users Access to Remote License Managers Access from Remote Clients Client Identities **Detachable Licenses**

On-Demand Detaching of Licenses

Enabled ☒

Maximum Duration @ 14 days

Automatic Detaching of Licenses

Enabled ☐

Allowed Offline Duration @ 2 hours

Common Detach Settings


Reserved Licenses @ 0 but at least 0 % of total licenses


Per Product Settings

3. Check **Enable Detaching of Licenses**.
4. Click **Submit**.



Detach a Key From the Server and Make it Available on the Client

1. On the client computer, from the Sentinel Admin Control Center in the Options panel, click **Products** to view all available local and network keys. Detachable keys have a red arrow  beside the Product Name and have a Detach button on the right.



2. Click the Detach button to make the key available to this client computer. The Detach form appears.

Detach License Host Name: manel-pc

Product: RASWin 2019 Full (ID:23)
Vendor: 24790 (ID:24790)
Available Licenses: 6 available for detaching
Max. Duration: 30 days
Sentinel Key: 817834342219452287
License Host: solidsafeserver

Detach Method:

- ☒ **Online** Detach license from solidsafeserver and automatically attach it to manel-pc
☐ **Offline** Detach license as an H2R file for use on the recipient machine selected below:

adria-pc - 192.168.1.134

Concurrency:

☐ Allow Concurrency for Detached Licenses

Total Number of Seats:

Detach of multiple seats is allowed only for a cloud license with a limited number of seats.

Expiration Date for Detached License:

Day: 29 Month: 3 Year: 2023 03/29/2023

Comment (optional):

Detach & Attach

Cancel

3. Set the Expiration Date, the day the license will be restored to the server license pool, and click Detach & Attach. The selected date must be within the maximum number of days for which the license can be detached.

The license is temporarily attached to this client computer. The license key is returned to the network license pool when the expiration date is reached.



Returning a Detached Key to the License Pool Before the Expiration Date

You can override the expiration date for the temporary key on the client computer and return it to the license pool on the server at any time before the expiration date.

1. On the client computer, from the Sentinel Admin Control Center in the Options panel, click **Products** to view all available local and network keys. The detached key is marked with a green arrow ➡ and has a Cancel License button to the right.

Sentinel Admin Control Center						
Sentinel Keys	Products Host Name: manel-pc					
Products	Product Name	Vendor	Location	Detached	Available	Actions
Features	Test Feature 1	DEMOMA - evaluation	Local	n/a		Features
Sessions	ISM Full	↔ 24790	solidsafeserver	n/a	6	Detach Features
Update/Attach	RASWin 2019 Full	↔ 24790	solidsafeserver	n/a	5	Detach / Extend Features
Access Log	RASWin 2019 Full	➡ 24790	Local			Cancel License Features
Configuration						
Diagnostics						

2. Click the **Cancel License** button and confirm your selection on the next page.

The license is now returned to the server license pool.